Manual

CodeMeter Network License

Version: 0.1

Versionen

Version	Änderungen	Datum	Bearbeiter
1	First version	05.02.26	ri

Inhaltsverzeichnis

1 General 3
2 Installation and Configuration 3
2.1 Download 3
2.2 Server Configuration 3
2.3 Client Configuration 4
3 Usage 5
4 Update or upgrade license 6

1 General

The network licenses offered are based **on** Wibu CodeMeter technology. Licenses are linked to a CodeMeter USB dongle, which, combined with the CodeMeter runtime, allows any computer to act as a license server.

Clients simply require the CodeMeter runtime to access available licenses over the network. Each license is valid for a defined period (e.g. three years), and a single dongle can host multiple licenses. Additionally, licenses can be upgraded or extended remotely.

2 Installation and Configuration

2.1 Download

To use the CodeMeter Network License the CodeMeter runtime is requied on the server and the client.


The CodeMeter runtime is available at https://www.wibu.com/support/user/user-software.html

2.2 Server Configuration


After installation the server needs to be activated at the CodeMeter WebAdmin.
By default this should be accessible via http://localhost:22352/

If this does not work, you can open the „**CodeMeter Control Center**“ and then go to the WebAdmin portal via the menu.

Within this WebAdmin the server configuration is available via the menu at „**Configuration**“ → „**Server**“ → „**Server access**“




Here you must to enable the network server.



2.3 Client Configuration

If the server is configured successfully the client should find the server automatically and, consequently, the available license.

If this is not the case the client can also be configured to search for the CodeMeter server at a specific IP address. This is done via **„Configuration“** → **„Basic“** → **„Server Search List“**.




Here servers can be added manually.

Also there are several settings like proxy.

3 Usage

If a CodeMeter network license is recognized by the tool you will find an info field via the menu „Settings“ → „License overview“

This will show some additional information about the network license.




If no network license is recognized, this field is hidden.

4 Update or upgrade license

It is possible to add additional licenses or upgrade licenses remotely.

For this, you will need to run the CodeMeter control center on the PC to which the dongle is connected.

1. Select the correct dongle and click the license update button



2. On the next two screens select the first option, afterwards select „emotas embedded communication GmbH“ and save the file.
3. Send the file to us. You will then receive a new file which can also be easily loaded by repeating step one and select the second option at the next screen.